

# Logging your Tripodmaker

## Install Printron

You can find the latest version of printron on this link:

<http://koti.kapsi.fi/~kliment/printron/>


## Install driver for windows

Install the driver you found attached to your e-mail. This is only necessary for windows. In case you installed RepetierHost for Tripodmaker in the past, you can skip this step.

## Connect your printer with the USB cable

To troubleshoot your USB connection, see other manual on Cable Connectivity Check.

## Configure Printron



Select the correct port that matches your printer or use "port button" to select the port. Keep in mind, after the first installation of the windows driver, reboot might be required. Be patient, it sometimes takes some time for the printer to show up.

Set baudrate to 115200 to get the connection going.